

**NAME**

**XSetWMColormapWindows**, **XGetWMColormapWindows** - set or read a window's WM\_COLORMAP\_WINDOWS property

**SYNTAX**

```
Status XSetWMColormapWindows(Display *display, Window w, Window *colormap_windows, int count);
```

```
Status XGetWMColormapWindows(Display *display, Window w, Window **colormap_windows_return, int *count_return);
```

**ARGUMENTS**

*display*      Specifies the connection to the X server.

*colormap\_windows*  
                Specifies the list of windows.

*colormap\_windows\_return*  
                Returns the list of windows.

*count*      Specifies the number of windows in the list.

*count\_return*      Returns the number of windows in the list.

*w*      Specifies the window.

**DESCRIPTION**

The **XSetWMColormapWindows** function replaces the WM\_COLORMAP\_WINDOWS property on the specified window with the list of windows specified by the colormap\_windows argument. If the property does not already exist, **XSetWMColormapWindows** sets the WM\_COLORMAP\_WINDOWS property on the specified window to the list of windows specified by the colormap\_windows argument. The property is stored with a type of WINDOW and a format of 32. If it cannot intern the WM\_COLORMAP\_WINDOWS atom, **XSetWMColormapWindows** returns a zero status. Otherwise, it returns a nonzero status.

**XSetWMColormapWindows** can generate **BadAlloc** and **BadWindow** errors.

The **XGetWMColormapWindows** function returns the list of window identifiers stored in the WM\_COLORMAP\_WINDOWS property on the specified window. These identifiers indicate the colormaps that the window manager may need to install for this window. If the property exists, is of

type `WINDOW`, is of format 32, and the atom `WM_COLORMAP_WINDOWS` can be interned. **XGetWMColormapWindows** sets the `windows_return` argument to a list of window identifiers, sets the `count_return` argument to the number of elements in the list, and returns a nonzero status. Otherwise, it sets neither of the return arguments and returns a zero status. To release the list of window identifiers, use **XFree**.

**XGetWMColormapWindows** can generate a **BadWindow** error.

## PROPERTIES

### WM\_COLORMAP\_WINDOWS

The list of window IDs that may need a different colormap from that of their top-level window.

## DIAGNOSTICS

**BadAlloc** The server failed to allocate the requested resource or server memory.

**BadWindow** A value for a `Window` argument does not name a defined Window.

## SEE ALSO

`XAllocClassHint(3)`, `XAllocIconSize(3)`, `XAllocSizeHints(3)`, `XAllocWMHints(3)`, `XFree(3)`,  
`XSetCommand(3)`, `XSetTransientForHint(3)`, `XSetTextProperty(3)`, `XSetWMClientMachine(3)`,  
`XSetWMIIconName(3)`, `XSetWMName(3)`, `XSetWMProperties(3)`, `XSetWMProtocols(3)`,  
`XStringListToTextProperty(3)`

*Xlib - C Language X Interface*