

NAME

XtParseAcceleratorTable, XtInstallAccelerators, XtInstallAllAccelerators - managing accelerator tables

SYNTAX

```
#include <X11/Intrinsic.h>
```

```
XtAccelerators XtParseAcceleratorTable(const char * source);
```

```
void XtInstallAccelerators(Widget destination, Widget source);
```

```
void XtInstallAllAccelerators(Widget destination, Widget source);
```

ARGUMENTS

source Specifies the accelerator table to compile.

destination Specifies the widget on which the accelerators are to be installed.

source Specifies the widget or the root widget of the widget tree from which the accelerators are to come.

DESCRIPTION

The **XtParseAcceleratorTable** function compiles the accelerator table into the opaque internal representation.

The **XtInstallAccelerators** function installs the accelerators from *source* onto *destination* by augmenting the *destination* translations with the *source* accelerators. If the *source* `display_accelerator` method is non-NULL, **XtInstallAccelerators** calls it with the *source* widget and a string representation of the accelerator table, which indicates that its accelerators have been installed and that it should display them appropriately. The string representation of the accelerator table is its canonical translation table representation.

The **XtInstallAllAccelerators** function recursively descends the widget tree rooted at *source* and installs the accelerators of each widget encountered onto *destination*. A common use is to call **XtInstallAllAccelerators** and pass the application main window as the *source*.

SEE ALSO

XtParseTranslationTable(1)

X Toolkit Intrinsics - C Language Interface

Xlib - C Language X Interface