

**NAME**

**dwarf\_init**, **dwarf\_elf\_init** - allocate a DWARF debug descriptor

**LIBRARY**

DWARF Access Library (libdwarf, -ldwarf)

**SYNOPSIS**

**#include <libdwarf.h>**

*int*

**dwarf\_init**(*int fd*, *int mode*, *Dwarf\_Handler errhand*, *Dwarf\_Ptr errarg*, *Dwarf\_Debug \*ret*,  
*Dwarf\_Error \*err*);

*in*

**dwarf\_elf\_init**(*Elf \*elf*, *int mode*, *Dwarf\_Handler errhand*, *Dwarf\_Ptr errarg*, *Dwarf\_Debug \*ret*,  
*Dwarf\_Error \*err*);

**DESCRIPTION**

These functions allocate and return a *Dwarf\_Debug* instance for the object denoted by argument *fd* or *elf*. This instance would be used for subsequent access to debugging information in the object by other functions in the DWARF(3) library.

For function **dwarf\_init**(), argument *fd* denotes an open file descriptor referencing a compilation object. Function **dwarf\_init**() implicitly allocates an *Elf* descriptor for argument *fd*.

For function **dwarf\_elf\_init**(), argument *elf* denotes a descriptor returned by *elf\_begin*(3) or *elf\_memory*(3).

Argument *mode* specifies the access mode desired. It should be at least as permissive as the mode with which the file descriptor *fd* or the ELF descriptor *elf* was created with. Legal values for argument *mode* are:

DW\_DLC\_RDWR Permit reading and writing of DWARF information.

DW\_DLC\_READ Operate in read-only mode.

DW\_DLC\_WRITE Permit writing of DWARF information.

Argument *errhand* denotes a function to be called in case of an error. If this argument is NULL then a default error handling scheme is used. See *dwarf*(3) for a description of the error handling scheme used by the DWARF(3) library.

Argument *errarg* is passed to the error handler function denoted by argument *errhand* when it is invoked.

Argument *ret* points to the memory location that will hold a *Dwarf\_Debug* reference on a successful call these functions.

Argument *err* references a memory location that would hold a *Dwarf\_Error* descriptor in case of an error.

### Memory Management

The *Dwarf\_Debug* instance returned by these functions should be freed using **dwarf\_finish()**.

### IMPLEMENTATION NOTES

The current implementation does not support access modes DW\_DLC\_RDWR and DW\_DLC\_WRITE.

### RETURN VALUES

These functions return the following values:

[DW_DLV_OK]	This return value indicates a successful return.
[DW_DLV_ERROR]	The operation failed.
[DW_DLV_NO_ENTRY]	The object specified by arguments <i>fd</i> or <i>elf</i> did not contain debug information.

### EXAMPLES

To initialize a *Dwarf\_Debug* instance from a open file descriptor referencing an ELF object, and with the default error handler, use:

```
Dwarf_Error err;  
Dwarf_Debug dbg;  
  
if (dwarf_init(fd, DW_DLC_READ, NULL, NULL, &dbg, &err) !=  
    DW_DLV_OK)  
    errx(EXIT_FAILURE, "dwarf_init: %s", dwarf_errmsg(err));
```

### SEE ALSO

dwarf(3), dwarf\_errmsg(3), dwarf\_finish(3), dwarf\_get\_elf(3), elf\_begin(3), elf\_memory(3)