

NAME

dwarf_lne_set_address - set the base address for line number information

LIBRARY

DWARF Access Library (libdwarf, -ldwarf)

SYNOPSIS

```
#include <libdwarf.h>
```

Dwarf_Unsigned

```
dwarf_lne_set_address(Dwarf_P_Debug dbg, Dwarf_Addr off, Dwarf_Unsigned symndx,  
    Dwarf_Error *err);
```

DESCRIPTION

Function **dwarf_lne_set_address**() sets the base address used by subsequent invocations of the **dwarf_add_line_entry**(3) function.

Argument *dbg* should reference a DWARF producer instance allocated using **dwarf_producer_init**(3) or **dwarf_producer_init_b**(3).

Argument *off* specifies a relocatable program address.

Argument *symndx* specifies the index of the ELF symbol to be used for relocation.

If argument *err* is not NULL, it will be used to store error information in case of an error.

RETURN VALUES

On success, function **dwarf_lne_set_address**() returns DW_DLV_OK. In case of an error, function **dwarf_lne_set_address**() returns DW_DLV_NOCOUNT and sets the argument *err*.

ERRORS

Function **dwarf_lne_set_address**() can fail with:

[DW_DLE_ARGUMENT] Argument *dbg* was NULL.

[DW_DLE_ARGUMENT] The argument *symndx* had an illegal value.

[DW_DLE_MEMORY] An out of memory condition was encountered during the execution of the function.

SEE ALSO

dwarf(3), dwarf_add_directory_decl(3), dwarf_add_file_decl(3), dwarf_add_line_entry(3), dwarf_lne_end_sequence(3), dwarf_producer_init(3), dwarf_producer_init_b(3)