

NAME

git-column - Display data in columns

SYNOPSIS

```
git column [--command=<name>] [--[raw-]mode=<mode>] [--width=<width>]
          [--indent=<string>] [--nl=<string>] [--padding=<n>]
```

DESCRIPTION

This command formats the lines of its standard input into a table with multiple columns. Each input line occupies one cell of the table. It is used internally by other git commands to format output into columns.

OPTIONS

--command=<name>

Look up layout mode using configuration variable column.<name> and column.ui.

--mode=<mode>

Specify layout mode. See configuration variable column.ui for option syntax in **git-config(1)**.

--raw-mode=<n>

Same as --mode but take mode encoded as a number. This is mainly used by other commands that have already parsed layout mode.

--width=<width>

Specify the terminal width. By default *git column* will detect the terminal width, or fall back to 80 if it is unable to do so.

--indent=<string>

String to be printed at the beginning of each line.

--nl=<string>

String to be printed at the end of each line, including newline character.

--padding=<N>

The number of spaces between columns. One space by default.

EXAMPLES

Format data by columns:

```
$ seq 1 24 | git column --mode=column --padding=5
1  4  7  10 13 16 19 22
2  5  8  11 14 17 20 23
3  6  9  12 15 18 21 24
```

Format data by rows:

```
$ seq 1 21 | git column --mode=row --padding=5
1  2  3  4  5  6  7
8  9 10 11 12 13 14
15 16 17 18 19 20 21
```

List some tags in a table with unequal column widths:

```
$ git tag --list 'v2.4.*' --column=row,dense
v2.4.0 v2.4.0-rc0 v2.4.0-rc1 v2.4.0-rc2 v2.4.0-rc3
v2.4.1 v2.4.10 v2.4.11 v2.4.12 v2.4.2
v2.4.3 v2.4.4 v2.4.5 v2.4.6 v2.4.7
v2.4.8 v2.4.9
```

CONFIGURATION

Everything below this line in this section is selectively included from the **git-config(1)** documentation. The content is the same as what's found there:

column.ui

Specify whether supported commands should output in columns. This variable consists of a list of tokens separated by spaces or commas:

These options control when the feature should be enabled (defaults to *never*):

always

always show in columns

never

never show in columns

auto

show in columns if the output is to the terminal

These options control layout (defaults to *column*). Setting any of these implies *always* if none of *always*, *never*, or *auto* are specified.

column

fill columns before rows

row

fill rows before columns

plain

show in one column

Finally, these options can be combined with a layout option (defaults to *nodense*):

dense

make unequal size columns to utilize more space

nodense

make equal size columns

column.branch

Specify whether to output branch listing in **git branch** in columns. See **column.ui** for details.

column.clean

Specify the layout when list items in **git clean -i**, which always shows files and directories in columns. See **column.ui** for details.

column.status

Specify whether to output untracked files in **git status** in columns. See **column.ui** for details.

column.tag

Specify whether to output tag listing in **git tag** in columns. See **column.ui** for details.

GIT

Part of the **git(1)** suite