

Name

`mysql_stmt_attr_get` - Gets the current value of a statement attribute

Synopsis

```
#include <mysql.h>

my_bool mysql_stmt_attr_get(MYSQL_STMT * stmt,
                           enum enum_stmt_attr_type,
                           void * attr);
```

Description

Gets the current value of a statement attribute. Returns zero on success, non zero on failure.

Parameter

- ⊕ `stmt` - a statement handle, which was previously allocated by **mysql_stmt_init(3)**.
- ⊕ `enum_stmt_attr_type` - attribute. See below.
- ⊕ `attr` - pointer to a variable, which will contain the attribute value.

Attribute types

The `enum_stmt_attr_type` parameter has the following possible values:

Value	Type	Description
<code>STMT_ATTR_UPDATE_MAX_LENGTH</code>	<code>my_bool *</code>	Indicates if <code>mysql_stmt_store_result(3)</code> will update the <code>max_length</code> value of <code>MYSQL_FIELD</code> structures.
<code>STMT_ATTR_CURSOR_TYPE</code>	<code>unsigned long *</code>	Possible values are <code>CURSOR_TYPE_READ_ONLY</code> or default value <code>CURSOR_TYPE_NO_CURSOR</code> .
<code>STMT_ATTR_PREFETCH_ROWS</code>	<code>unsigned long *</code>	Number of rows which will be prefetched. The default value is 1.
<code>STMT_ATTR_PREBIND_PARAMS</code>	<code>unsigned int *</code>	Number of parameters used for mariadb_stmt_execute_direct(3)
<code>STMT_ATTR_STATE</code>	<code>enum mysql_stmt_state</code>	Status of prepared statement.

*

Possible values are defined in enum mysql_stmt_state. This option was added in MariaDB Connector/C 3.1.0

Notes

- ⊕ Setting the number of prefetched rows will work only for read only cursors.

See Also

- ⊕ [mysql_stmt_attr_set\(3\)](#)