#### **NAME**

tcgetwinsize, tcsetwinsize - get, set the size of a terminal window

#### **LIBRARY**

```
Standard C Library (libc, -lc)
```

### **SYNOPSIS**

```
#include <termios.h>
```

```
struct winsize {
          unsigned short
                                                  /* number of rows, in characters */
                              ws_row;
          unsigned short
                                                  /* number of columns, in characters */
                              ws_col;
                                                  /* horizontal size, in pixels */
          unsigned short
                              ws xpixel;
          unsigned short
                              ws_ypixel;
                                                  /* vertical size, in pixels */
};
int
tcgetwinsize(int fd, struct winsize *w);
int
tcsetwinsize(int fd, const struct winsize *w);
```

# **DESCRIPTION**

The **tcgetwinsize**() function gets the terminal window size of the terminal of which fd is an open file descriptor and stores it in the *winsize* structure of which w is a pointer.

The **tcsetwinsize**() function sets the terminal window size of the terminal of which *fd* is an open file descriptor from the *winsize* structure referenced by *w*. The change occurs immediately. If the terminal window size of the terminal is changed successfully to have a value that is different from the value that it had before the **tcsetwinsize**() call, then the SIGWINCH signal is sent to all those members of the foreground process group of the terminal that have the terminal as their controlling terminal.

The above declaration of *struct winsize* may not be literal. It is provided only to list the accessible members. Therefore, before calling **tcsetwinsize**(), the members of the *winsize* structure must be initialized by calling **tcgetwinsize**(). The information in a *winsize* structure is stored by the kernel in order to provide a consistent interface, but it is not used by the kernel.

#### RETURN VALUE

The **tcgetwinsize**() and **tcsetwinsize**() functions return the value 0 if successful; otherwise the value -1 is returned and the global variable *errno* is set to indicate the error. The terminal window size remains

unchanged if tcsetwinsize() fails.

#### **ERRORS**

The following are the possible failure conditions:

[EBADF] The fd argument to tcgetwinsize() or to tcsetwinsize() is not a valid file descriptor.

[ENOTTY] The fd argument to tcgetwinsize() or to tcsetwinsize() is not associated with a

character special device.

[EINVAL] The w argument to **tcsetwinsize**() is not valid.

[EFAULT] The w argument to tcgetwinsize() or to tcsetwinsize() points outside the process's

allocated address space.

## **SEE ALSO**

stty(1), ioctl(2), sigaction(2), termios(4), tty(4)

#### **STANDARDS**

The **tcgetwinsize**() and **tcsetwinsize**() functions are expected to conform to IEEE Std 1003.1 ("POSIX.1") Base Specifications, Issue 8. The *ws\_xpixel* and *ws\_ypixel* members of *struct winsize* are FreeBSD extensions.