NAME
      RAND_get0_primary, RAND_get0_public, RAND_get0_private - get access to the global
      EVP_RAND_CTX instances

SYNOPSIS
      #include <openssl/rand.h>

      EVP_RAND_CTX *RAND_get0_primary(OSSL_LIB_CTX *ctx);
      EVP_RAND_CTX *RAND_get0_public(OSSL_LIB_CTX *ctx);
      EVP_RAND_CTX *RAND_get0_private(OSSL_LIB_CTX *ctx);

DESCRIPTION
      The default RAND API implementation (**RAND_OpenSSL()**) utilizes three shared DRBG instances
      which are accessed via the RAND API:

      The *public* and *private* DRBG are thread-local instances, which are used by **RAND_bytes()** and
      RAND_priv_bytes(), respectively. The *primary* DRBG is a global instance, which is not intended to be
      used directly, but is used internally to reseed the other two instances.

      These functions here provide access to the shared DRBG instances.

RETURN VALUES
      RAND_get0_primary() returns a pointer to the *primary* DRBG instance for the given OSSL_LIB_CTX
      ctx.

      RAND_get0_public() returns a pointer to the *public* DRBG instance for the given OSSL_LIB_CTX
      ctx.

      RAND_get0_private() returns a pointer to the *private* DRBG instance for the given OSSL_LIB_CTX
      ctx.

      In all the above cases the **ctx** parameter can be NULL in which case the default OSSL_LIB_CTX is
      used.

NOTES
      It is not thread-safe to access the *primary* DRBG instance. The *public* and *private* DRBG instance can
      be accessed safely, because they are thread-local. Note however, that changes to these two instances
      apply only to the current thread.

      For that reason it is recommended not to change the settings of these three instances directly. Instead,

an application should change the default settings for new DRBG instances at initialization time, before creating additional threads.

During initialization, it is possible to change the reseed interval and reseed time interval. It is also possible to exchange the reseeding callbacks entirely.

To set the type of DRBG that will be instantiated, use the **RAND_set_DRBG_type**(3) call before accessing the random number generation infrastructure.

SEE ALSO

EVP_RAND(3), **RAND_set_DRBG_type**(3)

HISTORY

These functions were added in OpenSSL 3.0.

COPYRIGHT