

NAME

tcpssso - set a socket option on a TCP endpoint

SYNOPSIS

```
tcpssso -i id [level] optname optval
tcpssso -a [level] optname optval
tcpssso -C cc-algo [-S stack] [-s state] [level] optname optval
tcpssso [-C cc-algo] [-S stack] [-s state] [level] optname optval
tcpssso [-C cc-algo] [-S stack] [-s state] [level] optname optval
```

DESCRIPTION

The **tcpssso** command applies a *level* level socket option with name *optname* and value *optval* on a TCP endpoint from the command line.

TCP endpoints in the SYN_RCVD state can only be handled by **tcpssso** if their prior state was SYN_SENT.

[*level*] can be specified as a non-negative number or a symbolic name like SOL_SOCKET, IPPROTO_IP, IPPROTO_IPV6, or IPPROTO_TCP. If not specified, **tcpssso** deduces the level from *optname*, if provided as a symbolic name. If that is not the case, IPPROTO_TCP is used.

optname can be specified as a non-negative number or a symbolic name like SO_DEBUG, IP_TOS, IPV6_TCLASS, TCP_LOG, TCP_CONGESTION, or TCP_FUNCTION_BLK.

optval can be an integer value, which will be converted to a binary value and passed as an int value. If it cannot be parsed as an integer value, it will be processed as a string. If the *optname* is TCP_FUNCTION_BLK then *optval* is converted to a *struct tcp_function_set*.

If **-i** *id* is specified then **tcpssso** will apply the socket option to the TCP endpoint with the *inp_gencnt* provided as *id*. The *inp_gencnt* for existing TCP endpoints can be determined by using `sockstat(1)`.

If **-a** is specified then **tcpssso** will apply the socket option to all TCP endpoints subject to the above state restrictions.

If **-C** *cc-algo* is specified then **tcpssso** will apply the socket option to all TCP endpoints using the TCP congestion control algorithm *cc-algo* and subject to the above state restrictions.

If **-S** *stack* is specified then **tcpssso** will apply the socket option to all TCP endpoints using the TCP stack *stack* and subject to the above state restrictions.

If **-s** *state* is specified then **tcpssso** will apply the socket option to all TCP endpoints being in the state *state*. *state* is one of CLOSED, LISTEN, SYN_SENT, SYN_RCVD, ESTABLISHED, CLOSE_WAIT, FIN_WAIT_1, CLOSING, LAST_ACK, FIN_WAIT_2, or TIME_WAIT. Using SYN_RCVD only applies to TCP endpoints in the state SYN_RCVD if their prior state was SYN_SENT.

If multiple of **-C** *cc-algo*, **-S** *stack*, and **-s** *state* are specified, **tcpssso** will apply the socket option to all TCP endpoints using the congestion control algorithm *cc-algo*, being in the state *state*, and using the TCP stack *stack*, if specified.

If none of the **-a**, **-C**, **-S**, or **-s** options are specified then the option **-i** must be specified.

EXIT STATUS

The **tcpssso** utility exits 0 on success, and >0 if an error occurs.

EXAMPLES

To diagnose a problem with a particular TCP connection to sshd(8), first determine its `inp_gencnt` using `sockstat(1)`:

```
# sockstat -4 -c -i -p 22 -P tcp -q
root  sshd      827  4 tcp4 \
      192.168.1.1:22    192.168.1.2:53736  435
```

Then, use the following command to enable Black Box Logging on it:

```
# tcpssso -i 435 TCP_LOG 4
```

To switch all TCP endpoints from using the `freebsd` stack to the `RACK` stack use:

```
# tcpssso -S freebsd TCP_FUNCTION_BLK rack
```

Switch all TCP endpoints in the `LISTEN` state to the `RACK` stack by using:

```
# tcpssso -s LISTEN TCP_FUNCTION_BLK rack
```

The following command will set the congestion control module of all TCP endpoints currently using `cubic` as its congestion control algorithm to the congestion control algorithm `newreno`:

```
# tcpssso -C cubic TCP_CONGESTION newreno
```

SEE ALSO

sockstat(1), setsockopt(2), tcp(4), tcp_functions(9)

HISTORY

The **tcpsso** command first appeared in FreeBSD 14.

AUTHORS

Michael Tuexen <*tuexen@FreeBSD.org*>