

NAME

vm_page_bits, **vm_page_set_validclean**, **vm_page_clear_dirty**, **vm_page_set_invalid**,
vm_page_zero_invalid, **vm_page_is_valid**, **vm_page_test_dirty**, **vm_page_dirty**, **vm_page_undirty** -
manage page clean and dirty bits

SYNOPSIS

```
#include <sys/param.h>
```

```
#include <vm/vm.h>
```

```
#include <vm/vm_page.h>
```

int

```
vm_page_bits(int base, int size);
```

void

```
vm_page_set_validclean(vm_page_t m, int base, int size);
```

void

```
vm_page_clear_dirty(vm_page_t m, int base, int size);
```

void

```
vm_page_set_invalid(vm_page_t m, int base, int size);
```

void

```
vm_page_zero_invalid(vm_page_t m, boolean_t setvalid);
```

int

```
vm_page_is_valid(vm_page_t m, int base, int size);
```

void

```
vm_page_test_dirty(vm_page_t m);
```

void

```
vm_page_dirty(vm_page_t m);
```

void

```
vm_page_undirty(vm_page_t m);
```

DESCRIPTION

vm_page_bits() calculates the bits representing the DEV_BSIZE range of bytes between *base* and *size*. The byte range is expected to be within a single page, and if *size* is zero, no bits will be set.

vm_page_set_validclean() flags the byte range between *base* and *size* as valid and clean. The range is expected to be DEV_BSIZE aligned and no larger than PAGE_SIZE. If it is not properly aligned, any unaligned chunks of the DEV_BSIZE blocks at the beginning and end of the range will be zeroed.

If *base* is zero and *size* is one page, the modified bit in the page map is cleared; as well, the VPO_NOSYNC flag is cleared.

vm_page_clear_dirty() clears the dirty bits within a page in the range between *base* and *size*. The bits representing the range are calculated by calling **vm_page_bits()**.

vm_page_set_invalid() clears the bits in both the valid and dirty flags representing the DEV_BSIZE blocks between *base* and *size* in the page. The bits are calculated by calling **vm_page_bits()**. As well as clearing the bits within the page, the generation number within the object holding the page is incremented.

vm_page_zero_invalid() zeroes all of the blocks within the page that are currently flagged as invalid. If *setvalid* is TRUE, all of the valid bits within the page are set.

In some cases, such as NFS, the valid bits cannot be set in order to maintain cache consistency.

vm_page_is_valid() checks to determine if all of the DEV_BSIZE blocks between *base* and *size* of the page are valid. If *size* is zero and the page is entirely invalid **vm_page_is_valid()** will return TRUE, in all other cases a size of zero will return FALSE.

vm_page_test_dirty() checks if a page has been modified via any of its physical maps, and if so, flags the entire page as dirty. **vm_page_dirty()** is called to modify the dirty bits.

vm_page_dirty() flags the entire page as dirty. It is expected that the page is not currently on the cache queue.

vm_page_undirty() clears all of the dirty bits in a page.

NOTES

None of these functions are allowed to block.

AUTHORS

This manual page was written by Chad David <davidc@acns.ab.ca>.