

NAME

bectl - Utility to manage boot environments on ZFS

SYNOPSIS

```
bectl [-h?]
bectl [-r beroot] activate [-t | -T] beName
bectl [-r beroot] check
bectl [-r beroot] create [-r] [-e {nonActiveBe | beName@snapshot}] newBeName
bectl [-r beroot] create [-r] beName@snapshot
bectl [-r beroot] destroy [-Fo] beName[@snapshot]
bectl [-r beroot] export sourceBe
bectl [-r beroot] import targetBe
bectl [-r beroot] jail [-bU] [{-o key=value | -u key}]... beName [utility [argument ...]]
bectl [-r beroot] list [-aDHs] [-c property] [-C property] [{-c property | -C property}]
bectl [-r beroot] mount beName [mountpoint]
bectl [-r beroot] rename origBeName newBeName
bectl [-r beroot] {ujail | unjail} {jailId | jailName | beName}
bectl [-r beroot] {umount | unmount} [-f] beName
```

DESCRIPTION

The **bectl** command is used to setup and interact with ZFS boot environments, which are bootable clones of datasets.

A boot environment allows the system to be upgraded, while preserving the pre-upgrade system environment.

bectl itself accepts an **-r** flag specified before the command to indicate the *beroot* that should be used as the boot environment root, or the dataset whose children are all boot environments. Normally this information is derived from the *bootfs* property of the pool that is mounted at */*, but it is useful when the system has not been booted into a ZFS root or a different pool should be operated on. For instance, booting into the recovery media and manually importing a pool from one of the system's resident disks will require the **-r** flag to work.

Supported Subcommands and Flags

-h | **-?** Print usage information.

activate [-t | -T] *beName*

Activate the given *beName* as the default boot filesystem. If the **-t** flag is given, this takes effect only for the next boot. Flag **-T** removes temporary boot once configuration. Without temporary configuration, the next boot will use zfs dataset specified in boot pool *bootfs*

property.

check Performs a silent sanity check on the current system. If boot environments are supported and used, **bectl** will exit with a status code of 0. Any other status code is not currently defined and may, in the future, grow special meaning for different degrees of sanity check failures.

create [-r] [-e {*nonActiveBe* | *beName@snapshot*}] *newBeName*
Create a new boot environment named *newBeName*.

If the **-r** flag is given, a recursive boot environment will be made. See *Boot Environment Structures* for a discussion on different layouts.

If the **-e** flag is specified, the new environment will be cloned from the given *nonActiveBe* or *beName@snapshot*. Otherwise, the new environment will be created from the currently booted environment.

If **bectl** is creating from another boot environment, a snapshot of that boot environment will be created to clone from.

create [-r] *beName@snapshot*
Create a snapshot of the boot environment named *beName*.

If the **-r** flag is given, a recursive snapshot of the boot environment will be created. A snapshot is created for each descendant dataset of the boot environment. See *Boot Environment Structures* for a discussion on different layouts.

No new boot environment is created with this subcommand.

destroy [-Fo] *beName*[@*snapshot*]
Destroy the given *beName* boot environment or *beName@snapshot* snapshot without confirmation, unlike in *beadm(1)*. Specifying **-F** will automatically unmount without confirmation.

By default, **bectl** will warn that it is not destroying the origin of *beName*. The **-o** flag may be specified to destroy the origin as well.

export *sourceBe*
Export *sourceBe* to *stdout(4)*. *stdout(4)* must be piped or redirected to a file.

import *targetBe*

Import *targetBe* from *stdin(4)*.

jail [-bU] [{-o *key=value* | -u *key*}]... *beName* [*utility* [*argument* ...]]

Create a jail of the given boot environment. Multiple **-o** and **-u** arguments may be specified. **-o** will set a jail parameter, and **-u** will unset a jail parameter.

By default, jails are created in interactive mode and */bin/sh* is executed within the jail. If *utility* is specified, it will be executed instead of */bin/sh*. The jail will be destroyed and the boot environment unmounted when the command finishes executing, unless the **-U** argument is specified.

The **-b** argument enables batch mode, thereby disabling interactive mode. The **-U** argument will be ignored in batch mode.

The *name*, *host.hostname*, and *path* must be set, the default values are specified below.

All *key=value* pairs are interpreted as jail parameters as described in *jail(8)*. The following default parameters are provided:

<i>allow.mount</i>	true
<i>allow.mount.devfs</i>	true
<i>enforce_statfs</i>	1
<i>name</i>	Set to jail ID.
<i>host.hostname</i>	<i>bootenv</i>
<i>path</i>	Set to a path in <i>/tmp</i> generated by <i>libbe(3)</i> .

All default parameters may be overwritten.

list [-aDHs] [{-c *property* | -C *property*}]

Display all boot environments. The *Active* field indicates whether the boot environment is active now (*N*); active on reboot (*R*); is used on next boot once (*T*); or combination of (*NRT*).

- a** Display all datasets.
- D** Display the full space usage for each boot environment, assuming all other boot environments were destroyed.
- H** Used for scripting. Do not print headers and separate fields by a single tab instead of arbitrary white space.

-s Display all snapshots as well.

-c *property*

Sort boot environments by the given ZFS dataset property. The following properties are supported:

- name (the default)
- creation
- origin
- used
- usedbydataset
- usedbyreservation
- usedbysnapshots

Short forms `usedds`, `usedreserv` and `usedsnap` are also supported.

-C *property*

Same as the **-c** option, but displays in descending order.

The **-D** option is ignored when either the **-s** or **-a** option is used.

mount *beName* [*mountpoint*]

Mount the given boot environment.

If a nonexistent *mountpoint* is given: **bectl** will make the directory, including intermediate directories as required.

If no *mountpoint* is given: **bectl** will make a directory such as *be_mount.c6Sf* in */tmp*. Randomness in the last four characters of the directory name will prevent mount point conflicts. Unmount of an environment, followed by mount of the same environment without giving a *mountpoint*, will result in a different randomly-named mountpoint.

rename *origBeName* *newBeName*

Rename the given *origBeName* to the given *newBeName*. The boot environment will not be unmounted in order for this rename to occur.

ujail {*jailId* | *jailName* | *beName*}

unjail {*jailId* | *jailName* | *beName*}

Destroy the jail created from the given boot environment.

umount [-f] *beName*

unmount [-f] *beName*

Unmount the given boot environment, if it is mounted. Specifying **-f** will force the unmount if busy.

Unmount will not remove the mount point.

Boot Environment Structures

The traditional FreeBSD boot environment layout, as created by the Auto ZFS option to `bsdinstall(8)`, is a "shallow" boot environment structure, where boot environment datasets do not have any directly subordinate datasets. Instead, they're organized off in `zroot/ROOT`, and they rely on datasets elsewhere in the pool having `canmount` set to off. For instance, a simplified pool may be laid out as such:

```
% zfs list -o name,canmount,mountpoint
NAME                                CANMOUNT    MOUNTPOINT
zroot
zroot/ROOT                          noauto      none
zroot/ROOT/default                  noauto      none
zroot/home                          on          /home
zroot/usr                          off         /usr
zroot/usr/src                       on          /usr/src
zroot/var                          off         /var
```

In that example, `zroot/usr` has `canmount` set to off, thus files in `/usr` typically fall into the boot environment because this dataset is not mounted. `zroot/usr/src` is mounted, thus files in `/usr/src` are not in the boot environment.

The other style of boot environments in use, frequently called "deep boot environments", organizes some or all of the boot environment as subordinate to the boot environment dataset. For example:

```
% zfs list -o name,canmount,mountpoint
NAME                                CANMOUNT    MOUNTPOINT
zroot
zroot/ROOT                          noauto      none
zroot/ROOT/default                  noauto      none
zroot/ROOT/default/usr              noauto      /usr
zroot/ROOT/default/usr/local        noauto      /usr/local
zroot/var                          on          /var
```

Note that the subordinate datasets now have `canmount` set to `noauto`. These are more obviously a part of the boot environment, as indicated by their positioning in the layout. These subordinate datasets will be mounted by the `zfsbe rc(8)` script at boot time. In this example, `/var` is excluded from the boot environment.

bectl subcommands that have their own **-r** operate on this second, "deep" style of boot environment, when the **-r** flag is set. A future version of **bectl** may default to handling both styles and deprecate the various **-r** flags.

SEE ALSO

`libbe(3)`, `zfsprops(7)`, `beinstall.sh(8)`, `jail(8)`, `zfs(8)`, `zpool(8)`

HISTORY

bectl is based on `beadm(1)` and was implemented as a project for the 2017 Summer of Code, along with `libbe(3)`.

AUTHORS

bectl was written by Kyle Kneitingner (`kneitingner`) <kyle@kneit.in>.

`beadm(1)` was written and is maintained by
Slawomir Wojciech Wojtczak (`vermaden`) <vermaden@interia.pl>.

Bryan Drewery (`bdrewery`) <bryan@shatow.net> wrote the original `beadm(1)` manual page that this one is derived from.