NAME

atan2, atan2f, atan2l, carg, cargf, cargl - arc tangent and complex phase angle functions

LIBRARY

```
Math Library (libm, -lm)
```

SYNOPSIS

```
#include <math.h>
double
atan2(double\ y,\ double\ x);
float
atan2f(float y, float x);
long double
atan2l(long\ double\ y,\ long\ double\ x);
#include <complex.h>
double
carg(double complex z);
float
cargf(float complex z);
long double
```

DESCRIPTION

cargl(long double complex z);

The atan2(), atan2f(), and atan2l() functions compute the principal value of the arc tangent of y/x, using the signs of both arguments to determine the quadrant of the return value.

The **carg()**, **cargf()**, and **cargl()** functions compute the complex argument (or phase angle) of z. The complex argument is the number theta such that $z = r * e^{(I * theta)}$, where r = cabs(z). The call carg(z)is equivalent to atan2(cimag(z), creal(z)), and similarly for cargf() and cargl().

RETURN VALUES

The atan2(), atan2f(), and atan2l() functions, if successful, return the arc tangent of y/x in the range [-pi, +pi] radians. Here are some of the special cases:

$$\begin{array}{ll} \mathbf{atan2}(y, \, x) := & \mathbf{atan}(y/x) & \text{if } x > 0, \\ & \mathrm{sign}(y)^*(\mathrm{pi-atan}(|y/x|)) & \text{if } x < 0, \\ & 0 & \text{if } x = y = 0, \, \text{or} \\ & \mathrm{sign}(y)^*\mathrm{pi}/2 & \text{if } x = 0 \mathrel{!=} y. \end{array}$$

NOTES

The function **atan2**() defines "if x > 0," **atan2**(θ , θ) = 0 despite that previously **atan2**(θ , θ) may have generated an error message. The reasons for assigning a value to **atan2**(θ , θ) are these:

- 1. Programs that test arguments to avoid computing **atan2**(0, 0) must be indifferent to its value. Programs that require it to be invalid are vulnerable to diverse reactions to that invalidity on diverse computer systems.
- 2. The **atan2**() function is used mostly to convert from rectangular (x,y) to polar (r,theta) coordinates that must satisfy $x = r*\cos theta$ and $y = r*\sin theta$. These equations are satisfied when (x=0,y=0) is mapped to (r=0,theta=0). In general, conversions to polar coordinates should be computed thus:

```
r := hypot(x,y); ... := sqrt(x*x+y*y)
theta := atan2(y,x).
```

3. The foregoing formulas need not be altered to cope in a reasonable way with signed zeros and infinities on a machine that conforms to IEEE 754; the versions of hypot(3) and **atan2**() provided for such a machine are designed to handle all cases. That is why **atan2**(+-0, -0) = +-pi for instance. In general the formulas above are equivalent to these:

$$r := \operatorname{sqrt}(x * x + y * y); \text{ if } r = 0 \text{ then } x := \operatorname{copysign}(1, x);$$

SEE ALSO

```
acos(3), asin(3), atan(3), cabs(3), cos(3), cosh(3), math(3), sin(3), sinh(3), tanh(3)
```

STANDARDS

The atan2(), atan2f(), atan2l(), carg(), cargf(), and cargl() functions conform to ISO/IEC 9899:1999 ("ISO C99").