

NAME

environ - user environment

SYNOPSIS

*extern char **environ;*

DESCRIPTION

An array of strings, called the *environment* is made available to each process by `execve(2)` when a process begins. By convention these strings have the form *name=value*, and are referred to as "environment variables". A process can query, update, and delete these strings using the `getenv(3)`, `setenv(3)`, and `unsetenv(3)` functions, respectively. The shells also provide commands to manipulate the environment; they are described in the respective shell manual pages.

What follows is a list of environment variables typically seen on a UNIX system. It includes only those variables that a user can expect to see during their day-to-day use of the system, and is far from complete. Environment variables specific to a particular program or library function are documented in the *ENVIRONMENT* section of the appropriate manual page.

ENVIRONMENT

BLOCKSIZE	The size of the block units used by several disk-related commands, most notably <code>df(1)</code> , <code>du(1)</code> and <code>ls(1)</code> . BLOCKSIZE may be specified in units of a byte by specifying a number, in units of a kilobyte by specifying a number followed by 'K' or 'k', in units of a megabyte by specifying a number followed by 'M' or 'm', and in units of a gigabyte by specifying a number followed by 'G' or 'g'. Sizes less than 512 bytes or greater than a gigabyte are ignored. This variable is processed by the <code>getbsize(3)</code> function.
COLUMNS	The user's preferred width in column positions for the terminal. Utilities such as <code>ls(1)</code> and <code>who(1)</code> use this to format output into columns. If unset or empty, utilities will use an <code>ioctl(2)</code> call to ask the terminal driver for the width.
EDITOR	Default editor name.
EXINIT	A startup list of commands read by <code>ex(1)</code> and <code>vi(1)</code> .
HOME	A user's login directory, set by <code>login(1)</code> from the password file <code>passwd(5)</code> .
LANG	This variable configures all programs which use <code>setlocale(3)</code> to use the specified locale unless the <code>LC_*</code> variables are set.

LC_ALL	Overrides the values of LC_COLLATE, LC_CTYPE, LC_MESSAGES, LC_MONETARY, LC_NUMERIC, LC_TIME and LANG.
LC_COLLATE	Locale to be used for ordering of strings.
LC_CTYPE	Locale to be used for character classification (letter, space, digit, etc.) and for interpreting byte sequences as multibyte characters.
LC_MESSAGES	Locale to be used for diagnostic messages.
LC_MONETARY	Locale to be used for interpreting monetary input and formatting output.
LC_NUMERIC	Locale to be used for interpreting numeric input and formatting output.
LC_TIME	Locale to be used for interpreting dates input and for formatting output.
MAIL	The location of the user's mailbox instead of the default in /var/mail, used by mail(1), sh(1), and many other mail clients.
MANPATH	The sequence of directories, separated by colons, searched by man(1) when looking for manual pages.
NLSPATH	List of directories to be searched for the message catalog referred to by LC_MESSAGES. See catopen(3).
PAGER	Default paginator program. The program specified by this variable is used by mail(1), man(1), ftp(1), etc, to display information which is longer than the current display.
PATH	The sequence of directories, separated by colons, searched by csh(1), sh(1), system(3), execvp(3), etc, when looking for an executable file. PATH is set to "/usr/bin:/bin" initially by login(1).
POSIXLY_CORRECT	When set to any value, this environment variable modifies the behaviour of certain commands to (mostly) execute in a strictly POSIX-compliant manner.
PRINTER	The name of the default printer to be used by lpr(1), lpq(1), and lprm(1).
PWD	The current directory pathname.

SHELL	The full pathname of the user's login shell.
TERM	The kind of terminal for which output is to be prepared. This information is used by commands, such as <code>nroff(1)</code> (<i>ports/textproc/groff</i>) or <code>plot(1)</code> which may exploit special terminal capabilities. See <code>/usr/share/misc/termcap</code> (<code>termcap(5)</code>) for a list of terminal types.
TERMCAP	The string describing the terminal in TERM, or, if it begins with a '/', the name of the termcap file. See TERMPATH below, and <code>termcap(5)</code> .
TERMPATH	A sequence of pathnames of termcap files, separated by colons or spaces, which are searched for terminal descriptions in the order listed. Having no TERMPATH is equivalent to a TERMPATH of <code>\$HOME/.termcap:/etc/termcap</code> . TERMPATH is ignored if TERMCAP contains a full pathname.
TMPDIR	The directory in which to store temporary files. Most applications use either <code>/tmp</code> or <code>/var/tmp</code> . Setting this variable will make them use another directory.
TZ	The timezone to use when displaying dates. The normal format is a pathname relative to <code>/usr/share/zoneinfo</code> . For example, the command <pre>env TZ=America/Los_Angeles date</pre> displays the current time in California. See <code>tzset(3)</code> for more information.
USER	The login name of the user. It is recommended that portable applications use LOGNAME instead.

Further names may be placed in the environment by the **export** command and *name=value* arguments in `sh(1)`, or by the **setenv** command if you use `csh(1)`. It is unwise to change certain `sh(1)` variables that are frequently exported by *.profile* files, such as MAIL, PS1, PS2, and IFS, unless you know what you are doing.

The current environment variables can be printed with `env(1)`, `set(1)` or `printenv(1)` in `sh(1)` and `env(1)`, `printenv(1)` or the **printenv** built-in command in `csh(1)`.

SEE ALSO

`cd(1)`, `csh(1)`, `env(1)`, `ex(1)`, `login(1)`, `printenv(1)`, `sh(1)`, `execve(2)`, `execle(3)`, `getbsize(3)`, `getenv(3)`, `setenv(3)`, `setlocale(3)`, `system(3)`, `termcap(3)`, `termcap(5)`

HISTORY

The **environ** manual page appeared in Version 7 AT&T UNIX.