

NAME

krb5_crypto_getblocksize, **krb5_crypto_getconfoundsizer**, **krb5_crypto_getenctype**,
krb5_crypto_getpadsize, **krb5_crypto_overhead**, **krb5_decrypt**, **krb5_decrypt_EncryptedData**,
krb5_decrypt_ivec, **krb5_decrypt_ticket**, **krb5_encrypt**, **krb5_encrypt_EncryptedData**,
krb5_encrypt_ivec, **krb5_enctype_disable**, **krb5_enctype_keysize**, **krb5_enctype_to_string**,
krb5_enctype_valid, **krb5_get_wrapped_length**, **krb5_string_to_enctype** - encrypt and decrypt data, set
and get encryption type parameters

LIBRARY

Kerberos 5 Library (libkrb5, -lkrb5)

SYNOPSIS

```
#include <krb5.h>
```

krb5_error_code

krb5_encrypt(*krb5_context context*, *krb5_crypto crypto*, *unsigned usage*, *void *data*, *size_t len*,
*krb5_data *result*);

krb5_error_code

krb5_encrypt_EncryptedData(*krb5_context context*, *krb5_crypto crypto*, *unsigned usage*, *void *data*,
size_t len, *int kvno*, *EncryptedData *result*);

krb5_error_code

krb5_encrypt_ivec(*krb5_context context*, *krb5_crypto crypto*, *unsigned usage*, *void *data*, *size_t len*,
*krb5_data *result*, *void *ivec*);

krb5_error_code

krb5_decrypt(*krb5_context context*, *krb5_crypto crypto*, *unsigned usage*, *void *data*, *size_t len*,
*krb5_data *result*);

krb5_error_code

krb5_decrypt_EncryptedData(*krb5_context context*, *krb5_crypto crypto*, *unsigned usage*,
*EncryptedData *e*, *krb5_data *result*);

krb5_error_code

krb5_decrypt_ivec(*krb5_context context*, *krb5_crypto crypto*, *unsigned usage*, *void *data*, *size_t len*,
*krb5_data *result*, *void *ivec*);

krb5_error_code

krb5_decrypt_ticket(*krb5_context context*, *Ticket *ticket*, *krb5_keyblock *key*, *EncTicketPart *out*,

```
krb5_flags flags);
```

krb5_error_code
krb5_crypto_getblocksize(*krb5_context context*, *size_t *blocksize*);

krb5_error_code
krb5_crypto_getenctype(*krb5_context context*, *krb5_crypto crypto*, *krb5_enctype *enctype*);

krb5_error_code
krb5_crypto_getpadszie(*krb5_context context*, *size_t, *padszie*");

krb5_error_code
krb5_crypto_getconfoundszie(*krb5_context context*, *krb5_crypto crypto*, *size_t, *confoundszie*");

krb5_error_code
krb5_enctype_keyszie(*krb5_context context*, *krb5_enctype type*, *size_t *keyszie*);

krb5_error_code
krb5_crypto_overhead(*krb5_context context*, *size_t, *padszie*");

krb5_error_code
krb5_string_to_enctype(*krb5_context context*, *const char *string*, *krb5_enctype *etype*);

krb5_error_code
krb5_enctype_to_string(*krb5_context context*, *krb5_enctype etype*, *char **string*);

krb5_error_code
krb5_enctype_valid(*krb5_context context*, *krb5_enctype etype*);

void
krb5_enctype_disable(*krb5_context context*, *krb5_enctype etype*);

size_t
krb5_get_wrapped_length(*krb5_context context*, *krb5_crypto crypto*, *size_t data_len*);

DESCRIPTION

These functions are used to encrypt and decrypt data.

krb5_encrypt_ivvec() puts the encrypted version of *data* (of size *len*) in *result*. If the encryption type supports using derived keys, *usage* should be the appropriate key-usage. *ivec* is a pointer to a initial IV,

it is modified to the end IV at the end of the round. Ivec should be the size of If NULL is passed in, the default IV is used. **krb5_encrypt()** does the same as **krb5_encrypt_ivec()** but with *ivec* being NULL. **krb5_encrypt_EncryptedData()** does the same as **krb5_encrypt()**, but it puts the encrypted data in a *EncryptedData* structure instead. If *kvno* is not zero, it will be put in the (optional) *kvno* field in the *EncryptedData*.

krb5_decrypt_ivec(), **krb5_decrypt()**, and **krb5_decrypt_EncryptedData()** works similarly.

krb5_decrypt_ticket() decrypts the encrypted part of *ticket* with *key*. **krb5_decrypt_ticket()** also verifies the timestamp in the ticket, invalid flag and if the KDC haven't verified the transited path, the transit path.

krb5_enctype_keysize(), **krb5_crypto_getconfoundsizer()**, **krb5_crypto_getblocksize()**, **krb5_crypto_getenctype()**, **krb5_crypto_getpadsize()**, **krb5_crypto_overhead()** all returns various (sometimes) useful information from a crypto context. **krb5_crypto_overhead()** is the combination of **krb5_crypto_getconfoundsizer()**, **krb5_crypto_getblocksize** and **krb5_crypto_getpadsize** and return the maximum overhead size.

krb5_enctype_to_string() converts a encryption type number to a string that can be printable and stored. The strings returned should be freed with **free(3)**.

krb5_string_to_enctype() converts a encryption type strings to a encryption type number that can be used for other Kerberos crypto functions.

krb5_enctype_valid() returns 0 if the encrypt is supported and not disabled, otherwise and error code is returned.

krb5_enctype_disable() (globally, for all contexts) disables the *enctype*.

krb5_get_wrapped_length() returns the size of an encrypted packet by *crypto* of length *data_len*.

SEE ALSO

krb5_create_checksum(3), **krb5_crypto_init(3)**