

NAME

kvm - kernel memory interface

LIBRARY

Kernel Data Access Library (libkvm, -lkvm)

DESCRIPTION

The **kvm** library provides a uniform interface for accessing kernel virtual memory images, including live systems and crash dumps. Access to live systems is via `sysctl(3)` for some functions, and `mem(4)` and `kmem(4)` for other functions, while crash dumps can be examined via the core file generated by `savecore(8)`. The interface behaves similarly in both cases. Memory can be read and written, kernel symbol addresses can be looked up efficiently, and information about user processes can be gathered.

The `kvm_open()` function is first called to obtain a descriptor for all subsequent calls.

COMPATIBILITY

The **kvm** interface was first introduced in SunOS. A considerable number of programs have been developed that use this interface, making backward compatibility highly desirable. In most respects, the Sun **kvm** interface is consistent and clean. Accordingly, the generic portion of the interface (i.e., `kvm_open()`, `kvm_close()`, `kvm_read()`, `kvm_write()`, and `kvm_nlist()`) has been incorporated into the BSD interface. Indeed, many **kvm** applications (i.e., debuggers and statistical monitors) use only this subset of the interface.

The process interface was not kept. This is not a portability issue since any code that manipulates processes is inherently machine dependent.

Finally, the Sun **kvm** error reporting semantics are poorly defined. The library can be configured either to print errors to `stderr` automatically, or to print no error messages at all. In the latter case, the nature of the error cannot be determined. To overcome this, the BSD interface includes a routine, `kvm_geterr(3)`, to return (not print out) the error message corresponding to the most recent error condition on the given descriptor.

CROSS DEBUGGING

The **kvm** library supports inspection of crash dumps from non-native kernels. Only a limited subset of the **kvm** interface is supported for these dumps. To inspect a crash dump of a non-native kernel, the caller must provide a *resolver* function when opening a descriptor via `kvm_open2()`. In addition, the **kvm** interface defines an integer type (`kvaddr_t`) that is large enough to hold all valid addresses of all supported architectures. The interface also defines a new namelist structure type (`struct kvm_nlist`) for use with `kvm_nlist2()`. To avoid address truncation issues, the caller should use `kvm_nlist2()` and `kvm_read2()` in place of `kvm_nlist()` and `kvm_read()`, respectively. Finally, only a limited subset of

operations are supported for non-native crash dumps: **kvm_close()**, **kvm_geterr()**, **kvm_kerndisp()**, **kvm_open2()**, **kvm_native()**, **kvm_nlist2()**, and **kvm_read2()**.

SEE ALSO

kvm_close(3), **kvm_getargv(3)**, **kvm_getenvv(3)**, **kvm_geterr(3)**, **kvm_getloadavg(3)**, **kvm_getprocs(3)**, **kvm_getswapinfo(3)**, **kvm_kerndisp(3)**, **kvm_native(3)**, **kvm_nlist(3)**, **kvm_nlist2(3)**, **kvm_open(3)**, **kvm_open2(3)**, **kvm_openfiles(3)**, **kvm_read(3)**, **kvm_read2(3)**, **kvm_write(3)**, **sysctl(3)**, **kmem(4)**, **mem(4)**

HISTORY

The **kvm_native()**, **kvm_nlist2()**, **kvm_open2()**, and **kvm_read2()** functions first appeared in FreeBSD 11.0.