

NAME

rdma_join_multicast - Joins a multicast group.

SYNOPSIS

```
#include <rdma/rdma_cma.h>
```

```
int rdma_join_multicast (struct rdma_cm_id *id, struct sockaddr *addr, void *context);
```

ARGUMENTS

id	Communication identifier associated with the request.
addr	Multicast address identifying the group to join.
context	User-defined context associated with the join request.

DESCRIPTION

Joins a multicast group and attaches an associated QP to the group.

RETURN VALUE

Returns 0 on success, or -1 on error. If an error occurs, errno will be set to indicate the failure reason.

NOTES

Before joining a multicast group, the rdma_cm_id must be bound to an RDMA device by calling rdma_bind_addr or rdma_resolve_addr. Use of rdma_resolve_addr requires the local routing tables to resolve the multicast address to an RDMA device, unless a specific source address is provided. The user must call rdma_leave_multicast to leave the multicast group and release any multicast resources. After the join operation completes, if a QP is associated with the rdma_cm_id, it is automatically attached to the multicast group when the multicast event is retrieved by the user. Otherwise, the user is responsible for calling ibv_attach_mcast to bind the QP to the multicast group. The join context is returned to the user through the private_data field in the rdma_cm_event.

SEE ALSO

rdma_leave_multicast(3), rdma_bind_addr(3), rdma_resolve_addr(3), rdma_create_qp(3),
rdma_get_cm_event(3)