# **NAME**

vm\_page\_bits, vm\_page\_set\_validclean, vm\_page\_clear\_dirty, vm\_page\_set\_invalid, vm\_page\_zero\_invalid, vm\_page\_is\_valid, vm\_page\_test\_dirty, vm\_page\_dirty, vm\_page\_undirty manage page clean and dirty bits

# **SYNOPSIS**

```
#include <svs/param.h>
#include <vm/vm.h>
#include <vm/vm page.h>
int
vm_page_bits(int base, int size);
void
vm_page_set_validclean(vm_page_t m, int base, int size);
void
vm_page_clear_dirty(vm_page_t m, int base, int size);
void
vm_page_set_invalid(vm_page_t m, int base, int size);
void
vm_page_zero_invalid(vm_page_t m, boolean_t setvalid);
int
vm page is valid(vm page t m, int base, int size);
void
vm_page_test_dirty(vm_page_t m);
void
vm_page_dirty(vm_page_t m);
void
vm_page_undirty(vm_page_t m);
```

## DESCRIPTION

**vm\_page\_bits**() calculates the bits representing the DEV\_BSIZE range of bytes between *base* and *size*. The byte range is expected to be within a single page, and if *size* is zero, no bits will be set.

**vm\_page\_set\_validclean**() flags the byte range between *base* and *size* as valid and clean. The range is expected to be DEV\_BSIZE aligned and no larger than PAGE\_SIZE. If it is not properly aligned, any unaligned chunks of the DEV\_BSIZE blocks at the beginning and end of the range will be zeroed.

If *base* is zero and *size* is one page, the modified bit in the page map is cleared; as well, the VPO\_NOSYNC flag is cleared.

**vm\_page\_clear\_dirty**() clears the dirty bits within a page in the range between *base* and *size*. The bits representing the range are calculated by calling **vm\_page\_bits**().

**vm\_page\_set\_invalid**() clears the bits in both the valid and dirty flags representing the DEV\_BSIZE blocks between *base* and *size* in the page. The bits are calculated by calling **vm\_page\_bits**(). As well as clearing the bits within the page, the generation number within the object holding the page is incremented.

**vm\_page\_zero\_invalid**() zeroes all of the blocks within the page that are currently flagged as invalid. If *setvalid* is TRUE, all of the valid bits within the page are set.

In some cases, such as NFS, the valid bits cannot be set in order to maintain cache consistency.

**vm\_page\_is\_valid**() checks to determine if the all of the DEV\_BSIZE blocks between *base* and *size* of the page are valid. If *size* is zero and the page is entirely invalid **vm\_page\_is\_valid**() will return TRUE, in all other cases a size of zero will return FALSE.

vm\_page\_test\_dirty() checks if a page has been modified via any of its physical maps, and if so, flags
the entire page as dirty. vm\_page\_dirty() is called to modify the dirty bits.

**vm\_page\_dirty**() flags the entire page as dirty. It is expected that the page is not currently on the cache queue.

vm\_page\_undirty() clears all of the dirty bits in a page.

# **NOTES**

None of these functions are allowed to block.

# **AUTHORS**

This manual page was written by Chad David <\davidc@acns.ab.ca>.