

NAME

winpr-makecert - A tool to create X.509 certificates.

SYNOPSIS

```
winpr-makecert [-rdp] [-silent] [-live] [-format { crt | pem | pfx }] [-p password] [-n common_name]
[-y years] [-m months] [-len length] [-# serial] [-a { md5 | sha1 | sha256 | s384 | sha512 }] [-path
outputpath] [outputname]
```

DESCRIPTION

winpr-makecert is a tool for generating X.509 certificates modeled after the Windows command MakeCert. winpr-makecert aims to be command line compatible with MakeCert however not all options are supported or implemented yet.

Unimplemented features are not described here. They are marked as "Unsupported" in winpr-makecerts help.

In contrast to it's Windows counterpart winpr-makecert does, unless the **-live** option is given, always creates and save a certificate. If *outputname* isn't set it is tried to determine the host name of the computer the command is run on.

Warning: if the file already exists it will be overwritten without asking.

Without further options the generated certificates have the following properties:

- * 2048 bit long
- * sha256 as hash algorithm
- * the detected host name is used as common name
- * a time stamp is used as serial number
- * validity period of one year
- * saved in the current working directory in crt format

OPTIONS

-rdp

Dummy parameter. Can be used to quickly generate a certificate with default properties without specifying any further parameters.

-silent

Don't print the generated certificate to stdout.

-f format

Three formats are supported: crt, pem and pfx.

crt outputs the key and the certificate in a separate file each with the file endings *.key* and *.crt*.

pem outputs the key and certificate into a single file with the file ending *pem*.

And *pfx* outputs key and certificate into a *pkcs12* file with the ending *.pfx*.

-p password

Password to use if the *pfx* format is used as format.

-live

Don't write the key/certificate to disk. When used from the command line this can be thought as "dummy" mode.

-n common_name

The common name to use in the certificate.

-m months

Validity period in months.

-y years

Validity period in years. If months and years are specified the specified month parameter will take precedence.

-len length

Key length in bits to use.

-a { md5 | sha1 | sha256 | sha384 | sha512 }

The hashing algorithm to use.

-# serial

The serial number to use for the certificate.

-path

A directory where the certificate should be created in.

outputname

The base name of the created file(s). A suffix, the format specific suffix is appended to this name.

EXAMPLES

```
winpr-makecert -rdp
```

Creates a certificate with the default properties, saved to a file in the current working directory in *crt*

format named like the host. If the host is named freerdp the created files are called freerdp.key and freerdp.crt.

```
winpr-makecert -len 4096 -a sha384 -path /tmp -# 22 -m 144 -y 1 -format crt mycert
```

The command above creates the file /tmp/mycert.pem containing a key and a certificate with a length of 4096. It will use sha384 as hash algorithm. The certificate has the serial number 22 and is valid for 12 years (144 months).

EXIT STATUS

0 Successful program execution.

1 Otherwise.

SEE ALSO

MakeCert help page <URL: <https://msdn.microsoft.com/library/windows/desktop/aa386968.aspx> >

AUTHOR

FreeRDP <team@freerdp.com>