NAME

RAND_egd, RAND_egd_bytes, RAND_query_egd_bytes - query entropy gathering daemon

SYNOPSIS

```
#include <openssl/rand.h>
int RAND_egd_bytes(const char *path, int num);
int RAND_egd(const char *path);
int RAND_query_egd_bytes(const char *path, unsigned char *buf, int num);
```

DESCRIPTION

On older platforms without a good source of randomness such as "/dev/urandom", it is possible to query an Entropy Gathering Daemon (EGD) over a local socket to obtain randomness and seed the OpenSSL RNG. The protocol used is defined by the EGDs available at http://egd.sourceforge.net/ or http://prngd.sourceforge.net/.

RAND_egd_bytes() requests **num** bytes of randomness from an EGD at the specified socket **path**, and passes the data it receives into **RAND_add()**. **RAND_egd()** is equivalent to **RAND_egd_bytes()** with **num** set to 255.

RAND_query_egd_bytes() requests **num** bytes of randomness from an EGD at the specified socket **path**, where **num** must be less than 256. If **buf** is **NULL**, it is equivalent to **RAND_egd_bytes()**. If **buf** is **not NULL**, then the data is copied to the buffer and **RAND_add()** is not called.

OpenSSL can be configured at build time to try to use the EGD for seeding automatically.

RETURN VALUES

RAND_egd() and **RAND_egd_bytes()** return the number of bytes read from the daemon on success, or -1 if the connection failed or the daemon did not return enough data to fully seed the PRNG.

RAND_query_egd_bytes() returns the number of bytes read from the daemon on success, or -1 if the connection failed.

SEE ALSO

```
RAND_add(3), RAND_bytes(3), RAND(7)
```

COPYRIGHT

Copyright 2000-2018 The OpenSSL Project Authors. All Rights Reserved.

3.0.11 2023-09-19 RAND_EGD(3ossl)

Licensed under the Apache License 2.0 (the "License"). You may not use this file except in compliance with the License. You can obtain a copy in the file LICENSE in the source distribution or at https://www.openssl.org/source/license.html>.

3.0.11 2023-09-19 RAND_EGD(3ossl)