#### **NAME**

os-release - file describing the current OS and some of its attributes

### DESCRIPTION

The **os-release** file is a new-line separated list of key value pairs. The syntax of this file is a reduced sh(1) variable assignment with the following restrictions:

- Strings cannot be concatenated together
- No variable expansion is done
- All shell special characters must be quoted as documented in sh(1)
- Variable assignments must be included inside of double quotes if they contain characters outside of A-Z, a-z and 0-9
- All strings should be UTF-8 format
- Non-printable characters should not be used in the strings

Lines starting with the character '#' are ignored as comments.

# **VARIABLES**

The following variables are defined by the standard.

NAME A string describing the preferred OS name.

VERSION Version string for the OS, in its usual and customary format.

ID Lower case version of the name with only a-z, 0-9, '.', '-', and '\_'.

VERSION ID Lower case version of the version with only a z 0.0 '.' '.' and '.'

VERSION\_ID Lower case version of the version with only a-z, 0-9, '.', '-', and '\_'.

PRETTY\_NAME

A pretty version of the name presented to the user. May contain release information.

ANSI\_COLOR Suggested color presentation for the OS. This string should be suitable for inclusion

within an ESC [ m ANSI/ECMA-48 escape sequence to render the OS in its

preferred color. This variable is optional.

CPE\_NAME A CPE name for the operating system. This field shall follow the NIST Common

Platform Enumeration specification.

HOME\_URL

SUPPORT\_URL

BUG\_REPORT\_URL

PRIVACY\_POLICY\_URL

Links on the internet, in RFC 3986 format for different aspects of this OS. These

OS-RELEASE(5) FreeBSD File Formats Manual OS-RELEASE(5)

variables are optional.

BUILD\_ID A string identifying the build. This variable is optional.

VARIANT A string describing the variant of this operating system. This variable is optional.

VARIANT\_ID Lower case version of the variant with only a-z, 0-9, '.', '-', and '\_'. This variable is

optional.

All other variables have no standard-defined meaning.

### **FILES**

/etc/os-release Symbolic link to actual os-release file.

/var/run/os-release

Generated os-release file describing the currently running system.

## **SEE ALSO**

**CPE Specification** 

https://csrc.nist.gov/projects/security-content-automation-protocol/scap-specifications/cpe

RFC 3986 https://tools.ietf.org/html/rfc3986

os-release Specification

https://www.linux.org/docs/man5/os-release.html

## **HISTORY**

This file first appeared in FreeBSD 13.0.