

NAME

xcb_xc_misc_get_version -

SYNOPSIS

```
#include <xcb/xc_misc.h>
```

Request function

```
xcb_xc_misc_get_version_cookie_t xcb_xc_misc_get_version(xcb_connection_t *conn,  
uint16_t client_major_version, uint16_t client_minor_version);
```

Reply datastructure

```
typedef struct xcb_xc_misc_get_version_reply_t {  
    uint8_t response_type;  
    uint8_t pad0;  
    uint16_t sequence;  
    uint32_t length;  
    uint16_t server_major_version;  
    uint16_t server_minor_version;  
} xcb_xc_misc_get_version_reply_t;
```

Reply function

```
xcb_xc_misc_get_version_reply_t *xcb_xc_misc_get_version_reply(xcb_connection_t *conn,  
xcb_xc_misc_get_version_cookie_t cookie, xcb_generic_error_t **e);
```

REQUEST ARGUMENTS

conn The XCB connection to X11.

client_major_version
 TODO: NOT YET DOCUMENTED.

client_minor_version
 TODO: NOT YET DOCUMENTED.

REPLY FIELDS

response_type The type of this reply, in this case `XCB_XC_MISC_GET_VERSION`. This field is also present in the `xcb_generic_reply_t` and can be used to tell replies apart from each other.

sequence The sequence number of the last request processed by the X11 server.

length The length of the reply, in words (a word is 4 bytes).

server_major_version
 TODO: NOT YET DOCUMENTED.

server_minor_version
 TODO: NOT YET DOCUMENTED.

DESCRIPTION

RETURN VALUE

Returns an *xcb_xc_misc_get_version_cookie_t*. Errors have to be handled when calling the reply function *xcb_xc_misc_get_version_reply*.

If you want to handle errors in the event loop instead, use *xcb_xc_misc_get_version_unchecked*. See **xcb-requests(3)** for details.

ERRORS

This request does never generate any errors.

SEE ALSO

AUTHOR

Generated from *xc_misc.xml*. Contact xcb@lists.freedesktop.org for corrections and improvements.