#### **NAME**

XkbResizeKeySyms - Change the number of symbols bound to a key

# **SYNOPSIS**

**KeySym \* XkbResizeKeySyms (XkbDescRec \****xkb*, int *key*, int *needed*);

#### **ARGUMENTS**

xkb keyboard description to be changed

key keycode for key to modify

needed

new number of keysyms required for key

# DESCRIPTION

XkbResizeKeySyms reserves the space needed for needed keysyms and returns a pointer to the beginning of the new array that holds the keysyms. It adjusts the offset field of the key\_sym\_map entry for the key if necessary and can also change the syms, num\_syms, and size\_syms fields of xkb->map if it is necessary to reallocate the syms array. XkbResizeKeySyms does not modify either the width or number of groups associated with the key.

If *needed* is greater than the current number of keysyms for the key, *XkbResizeKeySyms* initializes all new keysyms in the array to NoSymbol.

Because the number of symbols needed by a key is normally computed as width \* number of groups, and *XkbResizeKeySyms* does not modify either the width or number of groups for the key, a discrepancy exists upon return from *XkbResizeKeySyms* between the space allocated for the keysyms and the number required. The unused entries in the list of symbols returned by *XkbResizeKeySyms* are not preserved across future calls to any of the map editing functions, so you must update the key symbol mapping (which updates the width and number of groups for the key) before calling another allocator function. A call to *XkbChangeTypesOfKey* will update the mapping.

If any allocation errors occur while resizing the number of symbols bound to the key, *XkbResizeKeySyms* returns NULL.

# **SEE ALSO**

XkbChangeTypesOfKey(3), XkbResizeKeyActions(3)

#### **NOTES**

A change to the number of symbols bound to a key should be accompanied by a change in the number

of actions bound to a key. Refer to XkbResizeKeyActions for more information on changing the number of actions bound to a key.