NAME

gss_inquire_cred_by_mech - Obtain per-mechanism information about a credential

SYNOPSIS

```
#include <gssapi/gssapi.h>
```

```
OM uint32
```

```
gss_inquire_cred_by_mech(OM_uint32 *minor_status, const gss_cred_id_t cred_handle,
const gss_OID mech_type, gss_name_t *name, OM_uint32 *initiator_lifetime,
OM_uint32 *acceptor_lifetime, gss_cred_usage_t *cred_usage);
```

DESCRIPTION

Obtains per-mechanism information about a credential.

PARAMETERS

minor_status Mechanism specific status code.

cred_handle A handle that refers to the target credential. Specify GSS_C_NO_CREDENTIAL to

inquire about the default initiator principal.

mech_type The mechanism for which information should be returned.

name The name whose identity the credential asserts. Storage associated with this name

must be freed by the application after use with a call to gss_release_name(). Specify

NULL if not required.

initiator_lifetime The number of seconds for which the credential will remain capable of initiating

security contexts under the specified mechanism. If the credential can no longer be

used to initiate contexts, or if the credential usage for this mechanism is

GSS_C_ACCEPT, this parameter will be set to zero. If the implementation does not

support expiration of initiator credentials, the value GSS_C_INDEFINITE will be

returned. Specify NULL if not required.

acceptor lifetime

The number of seconds for which the credential will remain capable of accepting security contexts under the specified mechanism. If the credential can no longer be used to accept contexts, or if the credential usage for this mechanism is GSS_C_INITIATE, this parameter will be set to zero. If the implementation does not support expiration of acceptor credentials, the value GSS_C_INDEFINITE will be returned. Specify NULL if not required.

cred_usage How the credential may be used with the specified mechanism. One of the following:

GSS_C_INITIATE GSS_C_ACCEPT GSS_C_BOTH

Specify NULL if not required.

RETURN VALUES

GSS_S_COMPLETE Successful completion

GSS_S_NO_CRED The referenced credentials could not be accessed

GSS_S_DEFECTIVE_CREDENTIAL The referenced credentials were invalid

GSS_S_CREDENTIALS_EXPIRED The referenced credentials have expired. If the lifetime

parameter was not passed as NULL, it will be set to 0.

SEE ALSO

gss_release_name(3)

STANDARDS

RFC 2743 Generic Security Service Application Program Interface Version 2, Update 1

RFC 2744 Generic Security Service API Version 2 : C-bindings

HISTORY

The **gss_inquire_cred_by_mech** function first appeared in FreeBSD 7.0.

AUTHORS

John Wray, Iris Associates

COPYRIGHT

Copyright (C) The Internet Society (2000). All Rights Reserved.

This document and translations of it may be copied and furnished to others, and derivative works that comment on or otherwise explain it or assist in its implementation may be prepared, copied, published and distributed, in whole or in part, without restriction of any kind, provided that the above copyright notice and this paragraph are included on all such copies and derivative works. However, this document itself may not be modified in any way, such as by removing the copyright notice or references to the Internet Society or other Internet organizations, except as needed for the purpose of developing Internet standards in which case the procedures for copyrights defined in the Internet Standards process must be

followed, or as required to translate it into languages other than English.

The limited permissions granted above are perpetual and will not be revoked by the Internet Society or its successors or assigns.

This document and the information contained herein is provided on an "AS IS" basis and THE INTERNET SOCIETY AND THE INTERNET ENGINEERING TASK FORCE DISCLAIMS ALL WARRANTIES, EXPRESS OR IMPLIED, INCLUDING BUT NOT LIMITED TO ANY WARRANTY THAT THE USE OF THE INFORMATION HEREIN WILL NOT INFRINGE ANY RIGHTS OR ANY IMPLIED WARRANTIES OF MERCHANTABILITY OR FITNESS FOR A PARTICULAR PURPOSE.