### **NAME**

```
xcb_query_text_extents - get text extents
```

## **SYNOPSIS**

```
#include <xcb/xproto.h>
```

# **Request function**

```
xcb_query_text_extents_cookie_t xcb_query_text_extents(xcb_connection_t *conn, xcb_fontable_t font, uint32_t string_len, const xcb_char2b_t *string);
```

# Reply datastructure

```
typedef struct xcb_query_text_extents_reply_t {
    uint8_t response_type;
    uint8_t draw_direction;
    uint16_t sequence;
    uint32_t length;
    int16_t font_ascent;
    int16_t overall_ascent;
    int16_t overall_descent;
    int32_t overall_width;
    int32_t overall_left;
    int32_t overall_right;
} xcb_query_text_extents_reply_t;
```

# **Reply function**

```
xcb_query_text_extents_reply_t *xcb_query_text_extents_reply(xcb_connection_t *conn, xcb_query_text_extents_cookie_t cookie, xcb_generic_error_t **e);
```

# REQUEST ARGUMENTS

```
    The XCB connection to X11.
    The font to calculate text extents in. You can also pass a graphics context.
    The number of characters in string.
    The text to get text extents for.
```

### REPLY FIELDS

response\_type The type of this reply, in this case XCB\_QUERY\_TEXT\_EXTENTS. This field is also

present in the *xcb\_generic\_reply\_t* and can be used to tell replies apart from each

other.

sequence The sequence number of the last request processed by the X11 server.

length The length of the reply, in words (a word is 4 bytes).

draw\_direction One of the following values:

XCB\_FONT\_DRAW\_LEFT\_TO\_RIGHT
TODO: NOT YET DOCUMENTED.

XCB\_FONT\_DRAW\_RIGHT\_TO\_LEFT

TODO: NOT YET DOCUMENTED.

TODO: NOT YET DOCUMENTED.

font\_ascent TODO: NOT YET DOCUMENTED.

font\_descent TODO: NOT YET DOCUMENTED.

overall\_ascent TODO: NOT YET DOCUMENTED.

overall\_descent TODO: NOT YET DOCUMENTED.

overall\_width TODO: NOT YET DOCUMENTED.

overall\_left TODO: NOT YET DOCUMENTED.

overall\_right TODO: NOT YET DOCUMENTED.

### DESCRIPTION

Query text extents from the X11 server. This request returns the bounding box of the specified 16-bit character string in the specified *font* or the font contained in the specified graphics context.

font\_ascent is set to the maximum of the ascent metrics of all characters in the string. font\_descent is set to the maximum of the descent metrics. overall\_width is set to the sum of the character-width metrics of all characters in the string. For each character in the string, let W be the sum of the character-width metrics of all characters preceding it in the string. Let L be the left-side-bearing metric of the character plus W. Let R be the right-side-bearing metric of the character plus W. The lbearing

member is set to the minimum L of all characters in the string. The rbearing member is set to the maximum R.

For fonts defined with linear indexing rather than 2-byte matrix indexing, each  $xcb\_char2b\_t$  structure is interpreted as a 16-bit number with byte1 as the most significant byte. If the font has no defined default character, undefined characters in the string are taken to have all zero metrics.

Characters with all zero metrics are ignored. If the font has no defined default\_char, the undefined characters in the string are also ignored.

## **RETURN VALUE**

Returns an *xcb\_query\_text\_extents\_cookie\_t*. Errors have to be handled when calling the reply function *xcb\_query\_text\_extents\_reply*.

If you want to handle errors in the event loop instead, use *xcb\_query\_text\_extents\_unchecked*. See **xcb-requests(3)** for details.

#### **ERRORS**

```
xcb_font_error_t
```

The specified *font* does not exist.

xcb\_g\_context\_error\_t

The specified graphics context does not exist.

## **SEE ALSO**

**xcb-requests**(3)

# **AUTHOR**

Generated from xproto.xml. Contact xcb@lists.freedesktop.org for corrections and improvements.