NAME

zfs-project - manage projects in ZFS filesystem

SYNOPSIS

```
zfs project [-d|-r] file|directory<?>
zfs project -C [-kr] file|directory<?>
zfs project -c [-0] [-d|-r] [-p id] file|directory<?>
zfs project [-p id] [-rs] file|directory<?>
```

DESCRIPTION

```
zfs project [-d|-r] file|directory<?>
```

List project identifier (ID) and inherit flag of files and directories.

- -d Show the directory project ID and inherit flag, not its children.
- -r List subdirectories recursively.

```
zfs project -C [-kr] file|directory<?>
```

Clear project inherit flag and/or ID on the files and directories.

- -k Keep the project ID unchanged. If not specified, the project ID will be reset to zero.
- -r Clear subdirectories' flags recursively.

```
zfs project -c [-0] [-d|-r] [-p id] file|directory<?>
```

Check project ID and inherit flag on the files and directories: report entries without the project inherit flag, or with project IDs different from the target directory's project ID or the one specified with -p.

- -0 Delimit filenames with a NUL byte instead of newline, don't output diagnoses.
- -d Check the directory project ID and inherit flag, not its children.
- -p id Compare to id instead of the target files and directories' project IDs.
- **-r** Check subdirectories recursively.

```
zfs project -p id [-rs] file|directory<?>
```

Set project ID and/or inherit flag on the files and directories.

-p id Set the project ID to the given value.

- **-r** Set on subdirectories recursively.
- -s Set project inherit flag on the given files and directories. This is usually used for setting up tree quotas with -r. In that case, the directory's project ID will be set for all its descendants, unless specified explicitly with -p.

SEE ALSO

zfs-projectspace(8)